

DOSBox 0.74 Manual.txt
DOSBox v0.74 Manual (always use the
latest version from www.dosbox.com)

=====

NOTE:

=====

while we are hoping that one day
DOSBox will run all programs ever
made for
the PC, we are not there yet.
At present, DOSBox running on a
high-end machine will roughly be the
equivalent
of a Pentium I PC. DOSBox can be
configured to run a wide range of DOS
games,
from CGA/Tandy/PCjr classics up to
games from the Quake era.

=====

INDEX:

=====

DOSBox 0.74 Manual.txt

1. Quickstart
2. Start (FAQ)
3. Command Line Parameters
4. Internal Programs
5. Special Keys
6. Joystick/Gamepad
7. KeyMapper
8. Keyboard Layout
9. Serial Multiplayer feature
10. How to speed up/slow down DOSBox
11. Troubleshooting
12. DOSBox Status window
13. The configuration (options) file
14. The language file
15. Building your own version of
DOSBox
16. Special thanks
17. Contact

=====
1. Quickstart:
=====

Type INTRO in DOSBox for a quick

DOSBox 0.74 Manual.txt

tour.

It is essential that you get familiar with the idea of mounting, DOSBox does not

automatically make any drive (or a part of it) accessible to the emulation. See

the FAQ entry "How to start?" as well as the description of the MOUNT command

(section 4: "Internal Programs"). If you have your game on a cdrom you may try

this guide:

<http://vogons.zetafleet.com/viewtopic.php?t=8933>

=====

2. Start (FAQ):

=====

START: How to start?

AUTOMATION: Do I always have to type these "mount" commands?

FULLSCREEN: How do I change to

DOSBox 0.74 Manual.txt

fullscreen?

CD-ROM: My CD-ROM doesn't work.

CD-ROM: The game/application
can't find its CD-ROM.

MOUSE: The mouse doesn't work.

SOUND: There is no sound.

SOUND: what sound hardware does
DOSBox presently emulate?

SOUND: The sound stutters or
sounds stretched/weird.

KEYBOARD: I can't type \ or : in
DOSBox.

KEYBOARD: Right Shift and "\"
doesn't work in DOSBox. (Windows
only)

KEYBOARD: The keyboard lags.

CONTROL: The
character/cursor/mouse pointer always
moves into one direction!

SPEED: The game/application runs
much too slow/too fast!

CRASH: The game/application does
not run at all/crashes!

CRASH: DOSBox crashes on
startup!

GAME: My Build
game(Duke3D/Blood/Shadow warrior) has

DOSBox 0.74 Manual.txt

problems.

SAFETY: Can DOSBox harm my computer?

OPTIONS: I would like to change DOSBox's options.

HELP: Great Manual, but I still don't get it.

START: How to start?

At the beginning you've got a z:\> instead of a C:\> at the prompt.

You have to make your directories available as drives in DOSBox by using

the "mount" command. For example, in windows "mount C D:\GAMES" will give

you a C drive in DOSBox which points to your windows D:\GAMES directory

(that was created before). In Linux, "mount c /home/username" will give you

a C drive in DOSBox which points to /home/username in Linux.

DOSBox 0.74 Manual.txt

To change to the drive mounted like above, type "C:". If everything went fine, DOSBox will display the prompt "C:\>".

AUTOMATION: Do I always have to type these commands?

In the DOSBox configuration file is an [autoexec] section. The commands

present there are run when DOSBox starts, so you can use this section for the mounting. Look at Section 13: The configuration (options) file

FULLSCREEN: How do I change to fullscreen?

Press alt-enter. Alternatively: Edit the configuration file of DOSBox and

change the option fullscreen=false to fullscreen=true. If fullscreen looks

wrong in your opinion: Play with

DOSBox 0.74 Manual.txt

the options: fullresolution, output and

aspect in the configuration file of DOSBox. To get back from fullscreen

mode: Press alt-enter again.

CD-ROM: My CD-ROM doesn't work.

To mount your CD-ROM in DOSBox you have to specify some additional options

when mounting the CD-ROM.

To enable CD-ROM support (includes MSCDEX) in windows:

- mount d f:\ -t cdrom

in Linux:

- mount d /media/cdrom -t cdrom

In some cases you might want to use a different CD-ROM interface, for example if CD audio does not work:

To enable SDL-support (does not include low-level CD access!):

- mount d f:\ -t cdrom -used 0 -noioctl

DOSBox 0.74 Manual.txt

To enable ioctl access using digital audio extraction for CD audio (windows-only, useful for vista):

```
- mount d f:\ -t cdrom  
-ioctl_dx
```

To enable ioctl access using MCI for CD audio (windows-only):

```
- mount d f:\ -t cdrom  
-ioctl_mci
```

To force ioctl-only access (windows-only):

```
- mount d f:\ -t cdrom  
-ioctl_dio
```

To enable low-level aspi-support (win98 with aspi-layer installed):

```
- mount d f:\ -t cdrom -aspi
```

explanation: - d driveletter
you will get in DOSBox (d is the
best,

don't

change it!)

```
- f:\ location of  
CD-ROM on your PC. In most cases it  
will
```

DOSBox 0.74 Manual.txt

be d:\ or

e:\

- 0 The number of the CD-ROM drive, reported by "mount -cd"

(note that this value is only needed when using SDL

for CD audio, otherwise it is ignored)

See also the next question: The game/application can't find its CD-ROM.

CD-ROM: The game/application can't find its CD-ROM.

Be sure to mount the CD-ROM with -t cdrom switch, this will enable the MSCDEX interface required by DOS games to interface with CD-ROMs.

Also try adding the correct label (-label LABEL) to the mount command, where LABEL is the CD-label (volume ID) of the CD-ROM.

Under windows you can specify -ioctl, -aspi or -noioctl. Look at

DOSBox 0.74 Manual.txt

the

description of the mount command in Section 4: "Internal programs" for their meaning and the additional audio-CD related options `-ioctl_dx`, `ioctl_mci`, `ioctl_dio`.

Try creating a CD-ROM image (preferably CUE/BIN pair) and use the DOSBox's internal IMG MOUNT tool to mount the image (the CUE sheet).

This enables very good low-level CD-ROM support on any operating system.

MOUSE: The mouse doesn't work.

Usually, DOSBox detects when a game uses mouse control. When you click on

the screen it should get locked (confined to the DOSBox window) and work.

With certain games, the DOSBox mouse detection doesn't work. In that case

DOSBox 0.74 Manual.txt
you will have to lock the mouse manually by pressing CTRL-F10.

SOUND: There is no sound.

Be sure that the sound is correctly configured in the game.

This might be

done during the installation or with a setup/setsound utility that accompanies the game. First see if an autodetection option is provided. If

there is none try selecting Soundblaster or Soundblaster 16 with the default

settings being "address=220 irq=7 dma=1" (sometimes highdma=5). You might

also want to select Sound Canvas/SCC/MPU-401/General MIDI/Wave Blaster

at "address=330 IRQ=2" as music device.

The parameters of the emulated sound cards can be changed in the DOSBox

DOSBox 0.74 Manual.txt
configuration file.

If you still don't get any sound
set the core to normal in DOSBox
configuration and use some lower
fixed cycles value (like
cycles=2000). Also

assure that your host operating
sound does provide sound.

In certain cases it might be
useful to use a different emulated
sound device

like a soundblaster pro
(sctype=sbpro1 in the DOSBox
configuration file) or
the gravis ultrasound (gus=true).

SOUND: What sound hardware does
DOSBox presently emulate?

DOSBox emulates several legacy
sound devices:

- Internal PC speaker/Buzzer

This emulation includes both
the tone generator and several forms
of

digital sound output through
the internal speaker.

DOSBox 0.74 Manual.txt

- Creative CMS/Gameblaster

The is the first card released by Creative Labs(R). The default configuration places it on address 220. It is disabled as default.

- Tandy 3 voice

The emulation of this sound hardware is complete with the exception of

the noise channel. The noise channel is not very well documented and as

such is only a best guess as to the sound's accuracy. It is disabled as

default.

- Tandy DAC

Some games may require turning off sound blaster emulation (sbtype=none)

for better tandy DAC sound support. Don't forget to set the sbtype back to

sb16 if you don't use tandy sound.

- Adlib

DOSBox 0.74 Manual.txt

This emulation is almost perfect and includes the Adlib's ability to

almost play digitized sound.

Placed at address 220 (also on 388).

- SoundBlaster 16 / SoundBlaster Pro I & II / SoundBlaster I & II

By default DOSBox provides Soundblaster 16 level 16-bit stereo sound.

You can select a different SoundBlaster version in the configuration of

DOSBox. AWE32 music is not emulated as you can use MPU-401 instead

(see below).

- Disney Sound Source and Covox Speech Thing

Using the printer port, this sound device outputs digital sound only.

Placed at LPT1

- Gravis Ultrasound

The emulation of this hardware is nearly complete, though the MIDI capabilities have been left

DOSBox 0.74 Manual.txt
out, since an MPU-401 has been
emulated

in other code. For Gravis music
you also have to install Gravis
drivers

inside DOSBox. It is disabled
as default.

- MPU-401

A MIDI passthrough interface is
also emulated. This method of sound
output will only work when used
with external device/emulator.

Every windows XP/Vista/7 and
MAC OS has got a default emulator
compatible

with: Sound Canvas/SCC/General
Standard/General MIDI/Wave Blaster.

A different device/emulator is
needed for Roland LAPC/CM-32L/MT-32
compatibility.

SOUND: The sound stutters or sounds
stretched/weird.

You may be using too much CPU
power to keep DOSBox running at the
current

DOSBox 0.74 Manual.txt

speed. You can lower the cycles, skip frames, reduce the sampling rate of

the respective sound device, increase the prebuffer. See section 13: "The

configuration (options) file"

If you are using cycles=max or =auto, then make sure that there is no

background processes interfering! (especially if they access the harddisk)

Also look at Section 10. "How to speed up/slow down DOSBox"

KEYBOARD: I can't type \ or : in DOSBox.

This can happen in various cases, like your host keyboard layout does not

have a matching DOS layout representation (or it was not correctly

detected), or the key mapping is wrong.

DOSBox 0.74 Manual.txt

Some possible fixes:

1. Use / instead, or ALT-58 for : and ALT-92 for \.
2. Change the DOS keyboard layout (see Section 8: Keyboard Layout).
3. Add the commands you want to execute to the [autoexec] section of the DOSBox configuration file.
4. Open the DOSBox configuration file and change the usescancodes entry.
5. Switch the keyboard layout of your operating system.

Note that if the host layout can not be identified, or keyboardlayout is

set to none in the DOSBox configuration file, the standard US layout is

used. In this configuration try the keys around "enter" for the key \ (backslash), and for the key : (colon) use shift and the keys between

DOSBox 0.74 Manual.txt
"enter" and "L".

KEYBOARD: Right shift and "\" doesn't work in DOSBox. (Windows only)

This may happen if windows thinks that you have more than one keyboard connected to your PC when you use some remote control devices.

To verify this problem run cmd.exe, navigate to DOSBox program folder

and type:

set sdl_videodriver=windib

dosbox.exe

check whether keyboard started to work properly. As windib is slower it is

best to use one of the two solutions provided here:

<http://vogons.zetafleet.com/viewtopic.php?t=24072>

KEYBOARD: The keyboard lags.

Lower the priority setting in the

DOSBox 0.74 Manual.txt
DOSBox configuration file, for
example

set "priority=normal,normal". You
might also want to try lowering the
cycles (use a fixed cycle amount
to start with, like cycles=10000).

CONTROL: The character/cursor/mouse
pointer always moves into one
direction!

See if it still happens if you
disable the joystick emulation,
set joysticktype=none in the
[joystick] section of your DOSBox
configuration file. Maybe also
try unplugging any joystick/gamepad.

If you want to use the joystick
in the game, try setting timed=false
and be sure to calibrate the
joystick (both in your OS as well as
in the game or the game's setup
program).

SPEED: The game/application runs much
too slow/too fast!

DOSBox 0.74 Manual.txt

Look at the section 10: "How to speed up/slow down DOSBox" for more information.

CRASH: The game/application does not run at all/crashes!

Look at Section 11:
Troubleshooting

CRASH: DOSBox crashes on startup!.

Look at Section 11:
Troubleshooting

GAME: My Build
game(Duke3D/Blood/Shadow warrior) has
problems.

First of all, try to find a port
of the game. Those will offer a
better

experience. To fix the graphics
problem that occurs in DOSBox on
higher

resolutions: Open the
configuration file of DOSBox and

DOSBox 0.74 Manual.txt

search for

machine=svga_s3. Change svga_s3
to vesa_no1fb

Change memsize=16 to memsize=63

SAFETY: Can DOSBox harm my computer?

DOSBox can not harm your computer
more than any other resource
demanding

program. Increasing the cycles
does not overclock your real CPU.

Setting the cycles too high has a
negative performance effect on the
software running inside DOSBox.

OPTIONS: I would like to change
DOSBox's options.

Look at Section 13. "The
configuration (options) file"

HELP: Great Manual, but I still don't
get it.

For more questions read the rest
of this Manual. You may also look at:

DOSBox 0.74 Manual.txt
guides located at
<http://vogons.zetafleet.com/viewforum.php?f=39>
the wiki of DOSBox
<http://www.dosbox.com/wiki/>
the site/forum:
<http://www.dosbox.com>

=====
3. Command Line Parameters:
=====

An overview of the command line options you can give to DOSBox. Although in most cases it is easier to use DOSBox's configuration file instead. See: Section 13. "The configuration (options) file"

To be able to use Command Line Parameters:
(Windows) open cmd.exe or command.com or edit the shortcut to dosbox.exe

DOSBox 0.74 Manual.txt

(Linux) use console

(MAC OS X) start terminal.app and
navigate to:

```
/applications/dosbox.app/contents/mac  
os/dosbox
```

The options are valid for all
operating systems unless noted in the
option
description:

```
dosbox [name] [-exit] [-c command]  
[-fullscreen] [-userconf]  
[-conf configfilelocation]  
[-lang languagefilelocation]  
[-machine machine type]  
[-noconsole] [-startmapper]  
[-noautoexec]  
[-securemode] [-scaler scaler  
| -forcescaler scaler] [-version]  
[-socket socket]
```

```
dosbox -version
```

```
dosbox -editconf program
```

```
dosbox -opencaptures program
```

```
dosbox -printconf
```

DOSBox 0.74 Manual.txt

```
dosbox -eraseconf  
dosbox -erasemapper
```

name

If "name" is a directory it will mount that as the C: drive.

If "name" is an executable it will mount the directory of "name" as the C: drive and execute "name".

-exit

DOSBox will close itself when the DOS application "name" ends.

-c command

Runs the specified command before running "name". Multiple commands

can be specified. Each command should start with "-c" though.

A command can be: an Internal Program, a DOS command or an executable on a mounted drive.

DOSBox 0.74 Manual.txt

-fullscreen

Starts DOSBox in fullscreen mode.

-userconf

Start DOSBox with the users specific configuration file. Can be used

together with multiple **-conf** parameters, but **-userconf** will always be

loaded before them.

-conf configfilelocation

Start DOSBox with the options specified in "configfilelocation".

Multiple **-conf** options may be present.

See Section 13 for more details.

-lang languagefilelocation

Start DOSBox using the language specified in "languagefilelocation".

See Section 14 for more details.

DOSBox 0.74 Manual.txt

-machine machinetype

Setup DOSBox to emulate a specific type of machine. Valid choices are:

hercules, cga, ega, pcjr, tandy, svga_s3 (default) as well as the additional svga chipsets listed in the DOSBox configuration file.

svga_s3 enables vesa emulation as well.

For some special vga effects the machinetype vgaonly can be used, note that this disables svga capabilities and might be slower due to the

higher emulation precision.

The machinetype affects the video card and the available sound cards.

-noconsole (windows only)

Start DOSBox without showing DOSBox Status window (console).

Output will be redirected to stdout.txt and stderr.txt

DOSBox 0.74 Manual.txt

-startmapper

Enter the keymapper directly on startup. Useful for people with keyboard problems.

-noautoexec

Skips the [autoexec] section of the loaded configuration file.

-securemode

Same as -noautoexec, but adds config.com -securemode at the bottom of AUTOEXEC.BAT (which in turn disables any changes to how the drives are mounted inside DOSBox).

-scaler scaler

Uses the scaler specified by "scaler". See the DOSBox configuration file for the available scalers.

-forcescaler scaler

Similar to the -scaler parameter, but tries to force usage

DOSBox 0.74 Manual.txt

of

the specified scaler even if it might not fit.

-version

output version information and exit. Useful for frontends.

-editconf program

calls program with as first parameter the configuration file.

You can specify this command more than once. In this case it will move to second program if the first one fails to start.

-opencaptures program

calls program with as first parameter the location of the captures folder.

-printconf

prints the location of the default configuration file.

-resetconf

DOSBox 0.74 Manual.txt
removes the default
configuration file.

-resetmapper
removes the mapperfile used
by the default clean configuration
file.

-socket
passes the socket number to
the nullmodem emulation. See Section
9:
"Serial Multiplayer feature."

Note: If a
name/command/configfilelocation/langu
agefilelocation contains
a space, put the whole
name/command/configfilelocation/langu
agefilelocation
between quotes ("command or file
name"). If you need to use quotes
within
quotes (most likely with -c and
mount):
windows and OS/2 users can use
single quotes inside the double

DOSBox 0.74 Manual.txt

quotes.

Other people should be able to use escaped double quotes inside the double quotes.

Windows: -c "mount c 'c:\My folder with DOS games\'"

Linux: -c "mount c \"/tmp/name with space\""

A rather unusual example, just to demonstrate what you can do

(Windows):

```
dosbox D:\folder\file.exe -c "MOUNT Y H:\MyFolder"
```

This mounts D:\folder as C:\ and runs file.exe.

Before it does that, it will first mount H:\MyFolder as the Y drive.

In Windows, you can also drag directories/files onto the DOSBox executable.

=====

4. Internal Programs:

DOSBox 0.74 Manual.txt

=====

DOSBox supports most of the DOS commands found in command.com. To get a list of the internal commands type "HELP" at the prompt.

In addition, the following commands are available:

```
MOUNT "Emulated Drive letter" "Real
Drive or Directory"
      [-t type] [-aspi] [-ioctl]
      [-noioctl] [-usecd number] [-size
drivesize]
      [-label drivelabel] [-freesize
size_in_mb]
      [-freesize size_in_kb
(floppies)]
MOUNT -cd
MOUNT -u "Emulated Drive letter"
```

Program to mount local directories as drives inside DOSBox.

"Emulated Drive letter"

The driveletter inside DOSBox

DOSBox 0.74 Manual.txt
(for example C).

"Real Drive letter (usually for CD-ROMs in windows) or Directory"
The local directory you want accessible inside DOSBox.

-t type
Type of the mounted directory.
Supported are: dir (default), floppy, cdrom.

-size drivesize
(experts only)
Sets the size of the drive, where drivesize is of the form "bps,spc,tcl,fcl":
bps: bytes per sector, by default 512 for regular drives and 2048 for CD-ROM drives
spc: sectors per cluster, usually between 1 and 127
tcl: total clusters, between 1 and 65534
fcl: total free clusters,

DOSBox 0.74 Manual.txt
between 1 and tcl

`-freesize size_in_mb | size_in_kb`
Sets the amount of free space available on a drive in megabytes (regular drives) or kilobytes (floppy drives). This is a simpler version of `-size`.

`-label drivelabel`
Sets the name of the drive to "drivelabel". Needed on some systems if the CD-ROM label isn't read correctly (useful when a program can't find its CD-ROM). If you don't specify a label and no lowlevel support is selected (that is omitting the `-usedcd #` and/or `-aspi` parameters, or specifying `-noioctl`):
For windows: label is extracted from "Real Drive".
For Linux: label is set to `NO_LABEL`.

DOSBox 0.74 Manual.txt

If you do specify a label, this label will be kept as long as the drive is mounted. It will not be updated !!

-aspi

Forces use of the aspi layer. Only valid if mounting a CD-ROM under windows systems with an ASPI-Layer.

-ioctl (automatic selection of the CD audio interface)

-ioctl_dx (digital audio extraction used for CD audio)

-ioctl_dio (ioctl calls used for CD audio)

-ioctl_mci (MCI used for CD audio)

Forces use of ioctl commands. Only valid if mounting a CD-ROM under a windows OS which support them (win2000/XP/NT).

The various choices only differ in the way CD audio is handled,

preferably -ioctl_dio is used

DOSBox 0.74 Manual.txt
(lowest workload), but this might not
work on all systems, so
-ioctl_dx (or -ioctl_mci) can be
used.

-noioctl

Forces use of the SDL CD-ROM
layer. valid on all systems.

-usecd number

valid on all systems, under
windows the -noioctl switch has to be
present to make use of the
-usecd switch.

Enables to select the drive
that should be used by SDL. Use this
if

the wrong or no CD-ROM drive
is mounted while using the SDL CD-ROM
interface. "number" can be
found by "MOUNT -cd".

-cd

Displays all CD-ROM drives
detected by SDL, and their numbers.
See the information at the
-usecd entry above.

DOSBox 0.74 Manual.txt

-u

Removes the mount. Doesn't work for Z:\.

Note: It's possible to mount a local directory as CD-ROM drive, but hardware support is then missing.

Basically MOUNT allows you to connect real hardware to DOSBox's emulated PC.

So MOUNT C C:\GAMES tells DOSBox to use your C:\GAMES directory as drive C:

in DOSBox. MOUNT C E:\SomeFolder tells DOSBox to use your E:\SomeFolder directory as drive C: in DOSBox.

Mounting your entire C drive with MOUNT C C:\ is NOT recommended! The same

is true for mounting the root of any other drive, except for CD-ROMs (due to

DOSBox 0.74 Manual.txt

their read-only nature).

Otherwise if you or DOSBox make a mistake you may lose all your files.

Also never mount a "windows" or "Program Files" folders or their subfolders

in windows vista/7 as DOSBox may not work correctly, or will stop working

correctly later. It is recommended to keep all your dos applications/games

in a simple folder (for example c:\dosgames) and mount that.

You should always install your game inside DOSBox.

So if you have the game on CD you always (even after installation!)

have to mount both: folder as a harddisk drive and a CD-ROM.

HardDisk should always be mounted as c

CD-ROM should always be mounted as d

Floppy should always be mounted as a (or b)

DOSBox 0.74 Manual.txt

Basic MOUNT Examples for normal usage (Windows):

1. To mount a folder as a harddisk drive:

```
mount c d:\dosgames
```

3. To mount your CD-ROM drive E as CD-ROM drive D in DOSBox:

```
mount d e:\ -t cdrom
```

2. To mount your drive a: as a floppy:

```
mount a a:\ -t floppy
```

Advanced MOUNT examples (Windows):

4. To mount a hard disk drive with ~870 mb free disk space (simple version):

```
mount c d:\dosgames  
-freesize 870
```

5. To mount a drive with ~870 mb free disk space (experts only, full control):

DOSBox 0.74 Manual.txt

```
mount c d:\dosgames -size  
512,127,16513,13500
```

1. To mount c:\dosgames\floppy as a floppy:

```
mount a c:\dosgames\floppy  
-t floppy
```

Other MOUNT examples:

3. To mount system CD-ROM drive at mountpoint /media/cdrom as CD-ROM drive D

in DOSBox:

```
mount d /media/cdrom -t  
cdrom -usecd 0
```

6. To mount /home/user/dosgames as drive C in DOSBox:

```
mount c /home/user/dosgames
```

7. To mount the directory where DOSBox was started as C in DOSBox:

```
mount c .
```

(note the . which represents the directory where DOSBox

DOSBox 0.74 Manual.txt
was started,
on windows Vista/7 don't
use this if you installed DOSBox
to your "Program Files"
folder)

If you want to mount a CD image or
floppy image, check IMGMount.

MOUNT also works with images but
only if you use external program,
for example (both are free):

- Daemon Tools Lite (for CD
images),
- Virtual Floppy Drive (for floppy
images).

Although IMGMount can give better
compatibility.

MEM

Program to display the amount and
type of free memory.

VER

VER set major_version [minor_version]
Display the current DOSBox version

DOSBox 0.74 Manual.txt
and reported DOS version
(parameterless usage).
Change the reported DOS version
with the "set" parameter,
for example: "VER set 6 22" to have
DOSBox report DOS 6.22 as version
number.

```
CONFIG -writeconf filelocation  
CONFIG -writelang filelocation  
CONFIG -securemode  
CONFIG -set "section property=value"  
CONFIG -get "section property"
```

CONFIG can be used to change or
query various settings of DOSBox
during runtime. It can save the
current settings and language strings
to

disk. Information about all
possible sections and properties can
be found in Section 13: "The
configuration (options) file".

```
-writeconf filelocation  
Write the current configuration
```

DOSBox 0.74 Manual.txt
settings to a file in a specified
location.

"filelocation" is located on the
local drive, not a mounted drive in
DOSBox.

The configuration file controls
various settings of DOSBox:

the amount of emulated memory,
the emulated sound cards and many
more

things. It allows access to
AUTOEXEC.BAT as well.

See Section 13: "The
configuration (options) file" for
more information.

-writelang filelocation

Write the current language
settings to a file in a specified
location.

"filelocation" is located on the
local drive, not a mounted drive

in DOSBox. The language file
controls all visible output of the
internal

commands and the internal DOS.

See Section 14: "The Language

DOSBox 0.74 Manual.txt
File" for more information.

-securemode

Switches DOSBox to a more secure mode. In this mode the internal commands MOUNT, IMG MOUNT and BOOT won't work. It's not possible either

to create a new configfile or languagefile in this mode.

(Warning: you can only undo this mode by restarting DOSBox.)

-set "section property=value"

CONFIG will attempt to set the property to new value.

Currently CONFIG can not report whether the command succeeded or not.

-get "section property"

The current value of the property is reported and stored in the

environment variable %CONFIG%. This can be used to store the value when using batch files.

DOSBox 0.74 Manual.txt

Both "-set" and "-get" work from batch files and can be used to set up your

own preferences for each game. Although it may be easier to use separate

DOSBox's configuration files for each game instead.

Examples:

1. To create a configuration file in your c:\dosgames directory:

```
config -writeconf  
c:\dosgames\dosbox.conf
```

2. To set the cpu cycles to 10000:

```
config -set "cpu  
cycles=10000"
```

3. To turn ems memory emulation off:

```
config -set "dos ems=off"
```

4. To check which cpu core is being used.

```
config -get "cpu core"
```

LOADFIX [-size] [program]

DOSBox 0.74 Manual.txt

[program-parameters]

LOADFIX -f

Program to reduce the amount of available conventional memory.

Useful for old programs which don't expect much memory to be free.

-size

number of kilobytes to "eat up", default = 64kb

-f

frees all previously allocated memory

Examples:

1. To start mm2.exe and allocate 64kb memory

(mm2 will have 64 kb less available):

loadfix mm2

2. To start mm2.exe and allocate 32kb memory:

loadfix -32 mm2

3. To free previous allocated memory:

loadfix -f

DOSBox 0.74 Manual.txt

RESCAN

Make DOSBox reread the directory structure. Useful if you changed something

on a mounted drive outside of DOSBox. (CTRL - F4 does this as well!)

MIXER

Makes DOSBox display its current volume settings.

Here's how you can change them:

```
mixer channel left:right [/NOSHOW]
[/LISTMIDI]
```

channel

Can be one of the following:
MASTER, DISNEY, SPKR, GUS, SB, FM [,
CDAUDIO].

CDAUDIO is only available if a CD-ROM interface with volume control is

enabled (CD image, ioctl_dx).

DOSBox 0.74 Manual.txt

left:right

The volume levels in percentages. If you put a D in front it will be in decibel (Example: mixer gus d-10).

/NOSHOW

Prevents DOSBox from showing the result if you set one of the volume levels.

/LISTMIDI

In windows lists the available midi devices on your PC. To select a device

other than the windows default midi-mapper, change the line

'midiconfig='
in the [midi] section of the configuration file to

'midiconfig=id', where
'id' is the number for the device as listed by LISTMIDI. eg.
midiconfig=2

DOSBox 0.74 Manual.txt

In Linux this option doesn't work, but you get similar results by using

'pmidi -l' in console. Then change the line 'midiconfig=' to 'midiconfig=port', where 'port' is the port for the device as listed by

'pmidi -l'. eg. midiconfig=128:0

IMG MOUNT

A utility to mount disk images and CD-ROM images in DOSBox.

```
IMG MOUNT DRIVE [imagefile] -t
[image_type] -fs [image_format]
                -size [sectorsbytesize,
sectorsperhead, heads, cylinders]
IMG MOUNT DRIVE [imagefile1
imagefile2 .. imagefileN] -t cdrom
-fs iso
```

imagefile

Location of the image file to mount in DOSBox. The location can be on a mounted drive inside

DOSBox 0.74 Manual.txt

DOSBox, or on your real disk. It is possible

to mount CD-ROM images (ISOs or CUE/BIN or CUE/IMG) too.

If you need CD swapping capabilities, specify all images in succession

(see the next entry).

CUE/BIN pairs and cue/img are the preferred CD-ROM image types as they can

store audio tracks compared to ISOs (which are data-only). For

the CUE/BIN mounting always specify the CUE sheet.

imagefile1 imagefile2 .. imagefileN

Location of the image files to mount in DOSBox. Specifying a number of image files is only allowed for CD-ROM images.

The CD's can be swapped with CTRL-F4 at any time.

This is required for games which use multiple CD-ROMs and require the CD

to be switched during the

DOSBox 0.74 Manual.txt
gameplay at some point.

-t

The following are valid image types:

floppy: Specifies a floppy image. DOSBox will automatically identify

the disk geometry (360K, 1.2MB, 720K, 1.44MB, etc).

cdrom: Specifies a CD-ROM image. The geometry is automatic and set for this size.

This can be an iso or a cue/bin pair or

a cue/img pair.

hdd: Specifies a harddrive image. The proper CHS geometry must be set

for this to work.

-fs

The following are valid file system formats:

iso: Specifies the ISO 9660 CD-ROM format.

fat: Specifies that the

DOSBox 0.74 Manual.txt
image uses the FAT file system.
DOSBox will

attempt to mount this
image as a drive in DOSBox and make
the files available
from inside DOSBox.

none: DOSBox will make no
attempt to read the file system on
the disk.

This is useful if you
need to format it or if you want to
boot

the disk using the BOOT
command. When using the "none"
filesystem, you must
specify the drive number (2 or 3,
where 2 = master, 3 =
slave) rather than a drive letter.

For example, to mount a
70MB image as the slave drive device,
you would type (without
the quotes):

```
"imgmount 3  
d:\test.img -size 512,63,16,142 -fs  
none"
```

Compare this with a
mount to be able to access the drive

DOSBox 0.74 Manual.txt

within DOSBox, which would read as:

```
"imgmount e:  
d:\test.img -size 512,63,16,142"
```

-size

The Cylinders, Heads and Sectors of the drive.

Required to mount hard drive images.

An example how to mount CD-ROM images (in Linux):

```
1. imgmount d /tmp/cdimage1.cue  
/tmp/cdimage2.cue -t cdrom
```

or (which also works):

```
2a. mount c /tmp
```

```
2b. imgmount d c:\cdimage1.cue  
c:\cdimage2.cue -t cdrom
```

(in windows):

```
imgmount d f:\img\CD1.cue  
f:\img\CD2.cue f:\img\CD3.cue -t  
cdrom
```

```
imgmount d "g:\img\7th Guest  
CD1.cue" "g:\img\7th Guest CD2.cue"  
-t cdrom
```

Don't forget that you can also use

DOSBox 0.74 Manual.txt

MOUNT with images, but only if you use

external program, for example (both are free):

- Daemon Tools Lite (for CD images),
- Virtual Floppy Drive (for floppy images).

Although IMG MOUNT can give better compatibility.

BOOT

Boot will start floppy images or hard disk images independent of the operating system emulation offered by DOSBox. This will allow you to

play booter floppies or boot other operating systems inside DOSBox.

If the target emulated system is PCjr (machine=pcjr) the boot command can be used to load PCjr cartridges (.jrc).

```
BOOT [diskimg1.img diskimg2.img ..
diskimgN.img] [-l driveletter]
```

DOSBox 0.74 Manual.txt
BOOT [cart.jrc] (PCjr only)

diskimg1.img diskimg2.img ..
diskimgN.img

This can be any number of floppy disk images one wants mounted after DOSBox boots the specified drive letter.

To swap between images, hit CTRL-F4 to change from the current disk

to the next disk in the list. The list will loop back from the last disk image to the beginning.

[-l driveletter]

This parameter allows you to specify the drive to boot from.

The default is the A drive, the floppy drive. You can also boot

a hard drive image mounted as master by specifying "-l C"

without the quotes, or the drive as slave by specifying "-l D"

cart.jrc (PCjr only)

When emulation of a PCjr is

DOSBox 0.74 Manual.txt
enabled, cartridges can be loaded
with
the BOOT command. Support is
still limited.

IPX

You need to enable IPX networking
in the configuration file of DOSBox.

All of the IPX networking is
managed through the internal DOSBox
program

IPXNET. For help on the IPX
networking from inside DOSBox, type
"IPXNET HELP" (without quotes) and
the program will list the commands
and relevant documentation.

With regard to actually setting up
a network, one system needs to be
the server. To set this up, type
"IPXNET STARTSERVER" (without the
quotes)

in a DOSBox session. The server
DOSBox session will automatically add

DOSBox 0.74 Manual.txt
itself to the virtual IPX network.
For every additional computer that
should be part of the virtual IPX
network, you'll need to type
"IPXNET CONNECT <computer host name
or IP>".

For example, if your server is at
bob.dosbox.com, you would type
"IPXNET CONNECT bob.dosbox.com" on
every non-server system.

To play games that need Netbios a
file named NETBIOS.EXE from Novell is
needed. Establish the IPX
connection as explained above, then
run
"netbios.exe".

The following is an IPXNET command
reference:

IPXNET CONNECT

IPXNET CONNECT opens a
connection to an IPX tunneling server
running on another DOSBox
session. The "address" parameter

DOSBox 0.74 Manual.txt

specifies

the IP address or host name of the server computer. You can also specify the UDP port to use. By default IPXNET uses port 213 - the assigned IANA port for IPX tunneling - for its connection.

The syntax for IPXNET CONNECT is:

```
IPXNET CONNECT address <port>
```

IPXNET DISCONNECT

IPXNET DISCONNECT closes the connection to the IPX tunneling server.

The syntax for IPXNET DISCONNECT is:

```
IPXNET DISCONNECT
```

IPXNET STARTSERVER

IPXNET STARTSERVER starts an IPX tunneling server on this DOSBox session. By default, the server

DOSBox 0.74 Manual.txt
will accept connections on UDP port
213, though this can be changed.
Once the server is started, DOSBox
will automatically start a
client connection to the IPX
tunneling server.

The syntax for IPXNET
STARTSERVER is:
IPXNET STARTSERVER <port>

If the server is behind a
router, UDP port <port> needs to be
forwarded
to that computer.

On Linux/Unix-based systems port
numbers smaller than 1023 can only be
used with root privileges. Use
ports greater than 1023 on those
systems.

IPXNET STOPSERVER

IPXNET STOPSERVER stops the IPX
tunneling server running on this
DOSBox

DOSBox 0.74 Manual.txt
session. Care should be taken to ensure that all other connections have terminated as well, since stopping the server may cause lockups on other machines that are still using the IPX tunneling server.

The syntax for IPXNET STOPSERVER is:
IPXNET STOPSERVER

IPXNET PING

IPXNET PING broadcasts a ping request through the IPX tunneled network.

In response, all other connected computers will respond to the ping and report the time it took to receive and send the ping message.

The syntax for IPXNET PING is:
IPXNET PING

IPXNET STATUS

DOSBox 0.74 Manual.txt

IPXNET STATUS reports the current state of this DOSBox session's

IPX tunneling network. For a list of all computers connected to the

network use the IPXNET PING command.

The syntax for IPXNET STATUS is:
IPXNET STATUS

KEYB [keyboardlayoutcode [codepage [codepagefile]]]

Change the keyboard layout. For detailed information about keyboard layouts

please see section 8: "Keyboard Layout"

[keyboardlayoutcode] is a string consisting of five or less characters,

examples are PL214 (Polish

DOSBox 0.74 Manual.txt

typists) or PL457 (Polish programmers).

It specifies the keyboard layout to be used.

The list of all layouts built into DOSBox is here:

<http://vogons.zetafleet.com/viewtopic.php?t=21824>

[codepage] is the number of the codepage to be used. The keyboard layout

has to provide support for the specified codepage, otherwise the layout

loading will fail.

If no codepage is specified, an appropriate codepage for the requested

layout is chosen automatically.

[codepagefile] can be used to load codepages that are yet not compiled into DOSBox. This is only needed when DOSBox does not find the codepage.

DOSBox 0.74 Manual.txt

If no codepagefile is specified, but you place all ten ega.cpx files (from FreeDOS) in the DOSBox program folder, an appropriate codepagefile for the requested layout/codepage is chosen automatically.

Examples:

1. To load the polish typist keys layout (automatically uses codepage 852):

```
keyb pl214
```

2. To load one of russian keyboard layouts with codepage 866:

```
keyb ru441 866
```

In order to type russian characters press ALT+RIGHT-SHIFT.

3. To load one of french keyboard layouts with codepage 850 (where the codepage is defined in EGACPI.DAT):

```
keyb fr189 850 EGACPI.DAT
```

4. To load codepage 858 (without a keyboard layout):

```
keyb none 858
```

DOSBox 0.74 Manual.txt

This can be used to change the codepage for the FreeDOS keyb2 utility.

5. To display the current codepage and, if loaded, the keyboard layout:

keyb

For more information use the /? command line switch with the programs.

===== 5. Special Keys: =====

ALT-ENTER	Switch to full screen and back.
ALT-PAUSE	Pause emulation (hit ALT-PAUSE again to continue).
CTRL-F1	Start the keymapper.
CTRL-F4	Change between mounted floppy/CD images. Update directory

DOSBox 0.74 Manual.txt

cache

for all drives.

CTRL-ALT-F5 Start/Stop creating a movie of the screen. (avi video capturing)

CTRL-F5 Save a screenshot. (PNG format)

CTRL-F6 Start/Stop recording sound output to a wave file.

CTRL-ALT-F7 Start/Stop recording of OPL commands. (DRO format)

CTRL-ALT-F8 Start/Stop the recording of raw MIDI commands.

CTRL-F7 Decrease frameskip.

CTRL-F8 Increase frameskip.

CTRL-F9 Kill DOSBox.

CTRL-F10 Capture/Release the mouse.

CTRL-F11 Slow down emulation (Decrease DOSBox Cycles).

CTRL-F12 Speed up emulation (Increase DOSBox Cycles)*.

ALT-F12 Unlock speed (turbo button/fast forward)**.

F11, ALT-F11 (machine=cga) change tint in NTSC output modes***

F11 (machine=hercules)

DOSBox 0.74 Manual.txt
cycle through amber, green, white
colouring***

*NOTE: Once you increase your DOSBox
cycles beyond your computer CPU
resources,
it will produce the same
effect as slowing down the emulation.
This maximum will vary from
computer to computer.

**NOTE: You need free CPU resources
for this (the more you have, the
faster
it goes), so it won't work at
all with cycles=max or a too high
amount
of fixed cycles. You have to
keep the keys pressed for it to work!

***NOTE: These keys won't work if you
saved a mapper file earlier with
a different machine type. So
either reassign them or reset the
mapper.

These are the default keybindings.

DOSBox 0.74 Manual.txt

They can be changed in the keymapper (see Section 7: KeyMapper).

In MAC OS you can try using cmd(applekey) together with ctrl if the key doesn't work eg. cmd-ctrl-F1, but some keys may still need remapping (in Linux too).

Saved/recorded files can be found in:

(Windows) "Start/WinLogo
Menu"->"All
Programs"->DOSBox-0.74->Extras
(Linux) ~/.dosbox/capture
(MAC OS X)
"~/Library/Preferences/capture"

This can be changed in the DOSBox configuration file.

===== 6. Joystick/Gamepad: =====

The standard joystick port in DOS

DOSBox 0.74 Manual.txt
supports a maximum of 4 axes and 4
buttons.
For more, different modifications of
that configuration were used.

To force DOSBox to use a different
type of emulated joystick/gamepad,
the entry
"joysticktype" in the [joystick]
section of the DOSBox configuration
file can
be used.

none - disables controller support.
auto - (default) autodetects whether
you have one or two controllers
connected:

if you have one - '4axis'
setting is used,

if you have two - '2axis'
setting is used.

2axis - If you have two controllers
connected, each will emulate a
joystick

with 2 axes and 2 buttons. If
you have only one controller
connected,

DOSBox 0.74 Manual.txt
it will emulate a joystick
with only 2 axis and 2 buttons.
4axis - supports only first
controller, emulates a joystick
with 4 axis and 4 buttons or
a gamepad with 2axis and 6 buttons.
4axis_2 - supports only second
controller.
fcs - supports only first
controller, emulates ThrustMaster
Flight Control System, with
3-axes, 4 buttons and 1 hat.
ch - supports only first
controller, emulates CH Flightstick,
with 4-axes, 6 buttons and 1
hat, but you cannot press more
than one button at the same
time.

You also have to configure controller properly inside the game.

It is important to remember that if you saved the mapperfile without joystick

connected, or with a different

DOSBox 0.74 Manual.txt

joystick setting, your new setting will not work properly, or not work at all, until you reset DOSBox's mapperfile.

If controller is working properly outside DOSBox, but doesn't calibrate properly inside DOSBox, try different 'timed' setting in DOSBox's configuration file.

===== 7. KeyMapper: =====

You start the DOSBox mapper either with CTRL-F1 (see section 5. Special Keys) or -startmapper (see Section 3. Command Line Parameters). You are presented with a virtual

DOSBox 0.74 Manual.txt
keyboard and a virtual joystick.

These virtual devices correspond to the keys and events DOSBox will report to the DOS applications. If you click on a button with your mouse, you can see in the lower left corner with which event it is associated (EVENT) and to what events it is currently bound.

Event: EVENT
BIND: BIND (the real key/button/axis you push with your finger/hand)

Add Del
mod1 hold
Next
mod2
mod3

EVENT
The key or joystick
axis/button/hat DOSBox will report to

DOSBox 0.74 Manual.txt

DOS applications.

(the event that will happen during the game, (eg. shooting/jumping/walking))

BIND

The key on your real keyboard or the axis/button/hat on your real joystick(s) (as reported by SDL), which is connected to the EVENT.

mod1,2,3

Modifiers. These are keys you need to have to be pressed while pressing

BIND. mod1 = CTRL and mod2 = ALT. These are generally only used when you

want to change the special keys of DOSBox.

Add

Add a new BIND to this EVENT. Basically add a key from your keyboard or an

event from the joystick (button press, axis/hat movement) which will produce the EVENT in DOSBox.

Del

Delete the BIND to this EVENT. If

DOSBox 0.74 Manual.txt

an EVENT has no BINDS, then it is not possible to trigger this event in DOSBox (that is there's no way to type

the key or use the respective action of the joystick).

Next

Go through the list of bindings which map to this EVENT.

Example:

Q1. You want to have the X on your keyboard to type a Z in DOSBox.

A. Click on the Z on the keyboard mapper. Click "Add".

Now press the X key on your keyboard.

Q2. If you click "Next" a couple of times, you will notice that the Z on your

keyboard also produces an Z in DOSBox.

A. Therefore select the Z again, and click "Next" until you have the Z on

DOSBox 0.74 Manual.txt
your keyboard. Now click
"Del".

Q3. If you try it out in DOSBox, you will notice that pressing X makes ZX appear.

A. The X on your keyboard is still mapped to the X as well! Click on
the X in the keyboard mapper and search with "Next" until you find the
mapped key X. Click "Del".

Examples about remapping the joystick:

You have a joystick attached, it is working fine under DOSBox and you want to play some keyboard-only game with the joystick (it is assumed that the game is controlled by the arrows on the keyboard):

1. Start the mapper, then click on one of the left keyboard arrow.

EVENT should be key_left. Now click on Add and move your joystick

DOSBox 0.74 Manual.txt

in the respective direction, this should add an event to the BIND.

2. Repeat the above for the missing three directions, additionally

the buttons of the joystick can be remapped as well (fire/jump).

3. Click on Save, then on Exit and test it with some game.

You want to swap the y-axis of the joystick because some flightsim uses the up/down joystick movement in a way you don't like, and it is not configurable in the game itself:

1. Start the mapper and click on Y- in the first joystick field.

EVENT should be jaxis_0_1-.

2. Click on Del to remove the current binding, then click Add and move

your joystick downwards. A new bind should be created.

3. Repeat this for Y+, save the layout and finally test it with some game.

DOSBox 0.74 Manual.txt

If you want to remap anything to your d-pad/hat you will have to change

'joysticktype=auto' to 'joysticktype=fcs' in configuration file. Maybe this

will be improved in the next dosbox version.

If you change the default mapping, you can save your changes by clicking on

"Save". DOSBox will save the mapping to a location specified in the configuration file (the mapperfile= entry). At startup, DOSBox will load your mapperfile, if it is present in the DOSBox configuration file.

=====
8. Keyboard Layout:
=====

DOSBox 0.74 Manual.txt

To switch to a different keyboard layout, either the entry "keyboardlayout" in the [dos] section of the DOSBox configuration file can be used, or the internal DOSBox program keyb.com (Section 4: Internal Programs) Both accept DOS conforming language codes (see below), but only by using keyb.com a custom codepage can be specified.

The default keyboardlayout=auto currently works under windows only. The language is chosen according to the OS language, but the keyboard layout is not detected.

Layout switching

DOSBox supports a number of keyboard layouts and codepages by default, in this case just the layout identifier needs to be specified (like

DOSBox 0.74 Manual.txt

keyboardlayout=PL214 in the DOSBox configuration file, or using "keyb PL214"

at the DOSBox command prompt). The list of all layouts built into DOSBox is

here:

<http://vogons.zetafleet.com/viewtopic.php?t=21824>

Some keyboard layouts (for example layout GK319 codepage 869 and layout RU441

codepage 808) have support for dual layouts that can be accessed by pressing

LeftALT+RightSHIFT for one layout and LeftALT+LeftSHIFT for the other.

Some keyboard layouts (for example layout LT456 codepage 771) have support

for three layouts, third can be accessed by pressing LeftALT+LeftCTRL

Supported external files

The FreeDOS .kl files are supported (FreeDOS keyb2 keyboard layoutfiles)

DOSBox 0.74 Manual.txt

as

well as the FreeDOS
keyboard.sys/keybrd2.sys/keybrd3.sys
libraries which

consist of all available .kl files.

See <http://www.freedos.org/> for
precompiled keyboard layouts if
the DOSBox-integrated layouts don't
work for some reason, or if updated
or

new layouts become available.

Both .CPI (MS-DOS and compatible
codepage files) and .CPX (FreeDOS
UPX-compressed codepage files) can
be used. Some codepages are compiled
into DOSBox, so it is mostly not
needed to care about external
codepage

files. If you need a different (or
custom) codepage file, copy it into
the directory of the DOSBox so it
is accessible for DOSBox.

If you place all ten ega.cpx files
(from FreeDOS) in DOSBox folder,
an appropriate codepagefile for the
requested layout/codepage is

DOSBox 0.74 Manual.txt
chosen automatically.

Additional layouts can be added by copying the corresponding .kl file into

the directory of the DOSBox configuration file and using the first part of

the filename as language code.

Example: For the file UZ.KL (keyboard layout for Uzbekistan) specify

"keyboardlayout=uz" in the DOSBox configuration file.

The integration of keyboard layout packages (like keybrd2.sys) works similar.

Note that the keyboard layout allows foreign characters to be entered, but there is NO support for them in filenames. Try to avoid them both inside

DOSBox as well as in files on your host operating system that are accessible by DOSBox.

DOSBox 0.74 Manual.txt

```
=====
9. Serial Multiplayer feature:
=====
```

DOSBox can emulate a serial nullmodem cable over network and internet. It can be configured through the [serialports] section in the DOSBox configuration file.

To create a nullmodem connection, one side needs to act as the server and one as the client.

The server needs to be set up in the DOSBox configuration file like this:
serial1=nullmodem

The client:
serial1=nullmodem server:<IP or name of the server>

Now start your game and choose nullmodem / serial cable / already

DOSBox 0.74 Manual.txt

connected
as multiplayer method on COM1. Set
the same baudrate on both computers.

Furthermore, additional parameters
can be specified to control the
behavior
of the nullmodem connection. These
are all parameters:

- * port: - TCP port number.
Default: 23
- * rxdelay: - how long
(milliseconds) to delay received data
if the
interface is not
ready. Increase this value if you
encounter
overrun errors in
the DOSBox Status window. Default:
100
- * txdelay: - how long to gather
data before sending a packet.
Default: 12
(reduces Network
overhead)
- * server: - This nullmodem

DOSBox 0.74 Manual.txt
will be a client connecting to the
specified

server. (No server
argument: be a server.)

* transparent:1 - Only send the
serial data, no RTS/DTR handshake.
Use this

when connecting to
anything other than a nullmodem.

* telnet:1 - Interpret Telnet
data from the remote site.
Automatically

sets transparent.
* usedtr:1 - The connection
will not be established until DTR is
switched

on by the DOS
program. Useful for modem terminals.
Automatically sets
transparent.

* inhsocket:1 - Use a socket
passed to DOSBox by command line.
Automatically

sets transparent.
(Socket Inheritance: It is used for
playing old DOS
door games on new BBS software.)

DOSBox 0.74 Manual.txt

Example: Be a server listening on TCP port 5000.

```
serial1=nullmodem server:<IP or  
name of the server> port:5000  
rxdelay:1000
```

===== 10. How to speed up/slow down DOSBox: =====

DOSBox emulates the CPU, the sound and graphic cards, and other peripherals of a PC, all at the same time. The speed of an emulated DOS application depends on how many instructions can be emulated, which is adjustable (number of cycles).

CPU Cycles (speed up/slow down)

By default (cycles=auto) DOSBox tries to detect whether a game needs to

be run with as many instructions

DOSBox 0.74 Manual.txt
emulated per time interval as
possible

(cycles=max, sometimes this results
in game working too fast or
unstable),

or whether to use fixed amount of
cycles (cycles=3000, sometimes this
results

in game working too slow or too
fast). But you can always manually
force

a different setting in the DOSBox's
configuration file.

You can force the slow or fast
behavior by setting a fixed amount of
cycles

in the DOSBox's configuration file.
If you for example set cycles=10000,
then

DOSBox window will display a line
"Cpu Speed: fixed 10000 cycles" at
the top.

In this mode you can reduce the
amount of cycles even more by hitting
CTRL-F11

(you can go as low as you want) or

DOSBox 0.74 Manual.txt

raise it by hitting CTRL-F12 as much as you

want, but you will be limited by the power of one core of your computer's CPU.

You can see how much free time your real CPU's cores have by looking at the Task Manager in Windows 2000/XP/Vista/7 and the System Monitor

in Windows 95/98/ME. Once 100% of the power of your computer's real CPU's one

core is used, there is no further way to speed up DOSBox (it will actually

start to slow down), unless you reduce the load generated by the non-CPU parts

of DOSBox. DOSBox can use only one core of your CPU, so if you have

for example a CPU with 4 cores, DOSBox will not be able to use the power

of three other cores.

You can also force the fast

DOSBox 0.74 Manual.txt

behavior by setting `cycles=max` in the DOSBox

configuration file. The DOSBox window will display a line

"Cpu Speed: max 100% cycles" at the top then. This time you won't have to care

how much free time your real CPU's cores have, because DOSBox will always use

100% of your real CPU's one core. In this mode you can reduce the amount

of your real CPU's core usage by CTRL-F11 or raise it with CTRL-F12.

CPU Core (speed up)

On x86 architectures you can try to force the usage of a dynamically recompiling core (set `core=dynamic` in the DOSBox configuration file).

This usually gives better results if the auto detection (`core=auto`) fails.

It is best accompanied by `cycles=max`. But you may also try using it with

DOSBox 0.74 Manual.txt

high amounts of cycles (for example 20000 or more). Note that there might be

games that work worse/crash with the dynamic core (so save your game often),

or do not work at all!

Graphics emulation (speed up)

VGA emulation is a demanding part of DOSBox in terms of actual CPU usage.

Increase the number of frames skipped (in increments of one) by pressing

CTRL-F8. Your CPU usage should decrease when using a fixed cycle setting,

and you will be able to increase cycles with CTRL-F12.

You can repeat this until the game runs fast enough for you.

Please note that this is a trade-off: you lose in fluidity of video what

you gain in speed.

DOSBox 0.74 Manual.txt

Sound emulation (speed up)

You can also try to disable the sound through the setup utility of the game

to reduce load on your CPU further. Setting `nosound=true` in DOSBox's configuration does NOT disable the emulation of sound devices, just the output of sound will be disabled.

Also try to close every program but DOSBox to reserve as much resources as possible for DOSBox.

Advanced cycles configuration:

The `cycles=auto` and `cycles=max` settings can be parameterized to have different startup defaults. The syntax is

```
cycles=auto ["realmode default"]  
["protected mode default"%]  
           [limit "cycle limit"]  
cycles=max ["protected mode  
default"%] [limit "cycle limit"]
```

Example:

DOSBox 0.74 Manual.txt
cycles=auto 5000 80% limit 20000
will use cycles=5000 for real mode
games, 80% CPU throttling for
protected mode games along with a
hard cycle limit of 20000

=====
11. Troubleshooting:
=====

General tip:
Check messages in DOSBox Status
window. See section 12. "DOSBox
Status window"

DOSBox crashes right after starting
it:

- use different values for the
output= entry in your DOSBox
configuration file
- try to update your graphics card
driver and DirectX
- (Linux) set the environment
variable SDL_AUDIODRIVER to alsa or
OSS.

DOSBox 0.74 Manual.txt

Running a certain game closes DOSBox, crashes with some message or hangs:

- see if it works with a default DOSBox installation (unmodified configuration file)
- try it with sound disabled (use the sound configuration program that comes with the game, additionally you can set `sbttype=none` and `gus=false` in the DOSBox configuration file)
- change some entries of the DOSBox configuration file, especially try:
 - `core=normal`
 - `fixed cycles` (for example `cycles=10000`)
 - `ems=false`
 - `xms=false`or combinations of the above settings,
- similar the machine settings that control the emulated chipset and functionality:
 - `machine=vesa_nolfb`or
 - `machine=vgaonly`

DOSBox 0.74 Manual.txt

- use loadfix before starting the game

The game exits to the DOSBox prompt with some error message:

- read the error message closely and try to locate the error

- try the hints at the above sections

- mount differently as some games are picky about the locations, for example if you used "mount d d:\oldgames\game" try

"mount c d:\oldgames\game" and "mount c d:\oldgames"

- if the game requires a CD-ROM be sure you used "-t cdrom" when

mounting and try different additional parameters (the ioctl, usecd and label switches, see the appropriate section)

- check the file permissions of the game files (remove read-only attributes, add write permissions etc.)

- try reinstalling the game within DOSBox

DOSBox 0.74 Manual.txt

```
=====
```

12. DOSBox Status window:

```
=====
```

DOSBox's Status window contains many useful information about your current configuration, your actions in DOSBox, errors that happened and more.

Whenever you have any problem with DOSBox check these messages.

To start DOSBox Status window:

(Windows) Status window is being started together with main DOSBox window.

(Linux) You may have to start DOSBox from a console to see Status window.

(MAC OS X) Right click on DOSBox.app, choose "Show Package Contents"->

->enter

"Contents"->enter "MacOS"->run

"DOSBox"

=====
13. The configuration (options) file:
=====

The configuration file is automatically created the first time you run DOSBox.

The file can be found in:

(windows) "Start/winLogo
Menu"->"All
Programs"->DOSBox-0.74->Options
(Linux)
~/ .dosbox/dosbox-0.74.conf
(MAC OS X)
"~/Library/Preferences/DOSBox 0.74
Preferences"

The file is divided into several sections. Each section starts with a [section name] line. The settings are the property=value lines where value can

be altered to customize DOSBox.

and % indicate comment-lines.

DOSBox 0.74 Manual.txt

An extra configuration file can be generated by CONFIG.COM, which can be found

on the internal DOSBox Z: drive when you start up DOSBox. Look in the Section 4:

"Internal programs" for usage of CONFIG.COM. You can start DOSBox with the -conf switch to load the generated file and use its settings.

DOSBox will load configuration files that are specified with -conf. If none were

specified, it will try to load "dosbox.conf" from the local directory.

If there is none, DOSBox will load the user configuration file.

This file will be created if it doesn't exist.

Important!: In windows vista/7 the configuration file won't work correctly

DOSBox 0.74 Manual.txt
if it is located in "windows" or
"Program Files" folder or their
subfolders,
or directly on c:\, so the best place
for storing extra configuration files
is
for example: C:\oldgames

=====
14. The Language File:
=====

A language file can be generated by
CONFIG.COM, which can be found on the
internal DOSBox Z: drive when you
start up DOSBox. Look in the Section
4:

"Internal programs" for usage of
CONFIG.COM.

Read the language file, and you will
hopefully understand how to change
it.

Start DOSBox with the -lang switch to
use your new language file.

Alternatively, you can setup the

DOSBox 0.74 Manual.txt
filename in the configuration file
in the [dosbox] section. There's a
language= entry that can be changed
with
the filelocation.

=====

===

15. Building your own version of
DOSBox:

=====

===

Download the source.
Check the INSTALL in the source
distribution.

=====

16. Special thanks:

=====

See the THANKS file.

DOSBox 0.74 Manual.txt

=====
17. Contact:
=====

See the site:
<http://www.dosbox.com>
for an email address (The Crew-page).